



# How to setup Email account in Thunderbird

1. Launch Thunderbird
2. Go to Tools > Account Settings




3. Go to Account Actions > Add Mail Account



#### 4. Update settings as below and click <Configure manually>

- Your name : Enter sender name
- Email address : Enter Email address
- Password : Enter Email account password
- Remember password : Enable



Set Up Your Existing Email Address

Set Up Your Existing Email Address

Use your current email address

Your name:

Email address:  [Get a new email address...](#)

Password:

Remember password


## 5. (A) Update settings as below for IMAP and click <Done>

### <Incoming>

- Protocol : IMAP
- Server : You can find it in Support Letter > Hosting Email > IMAP Server Host
- Port : 993
- SSL : SSL/TLS
- Authentication : Normal Password
- Username : Enter Email address

### <Outgoing>

- Server : You can find it in Support Letter > Hosting Email > SMTP Server Host
- Port : 465
- SSL : SSL/TLS
- Authentication : Normal Password
- Username : Enter Email address



The screenshot shows the 'Incoming' and 'Outgoing' configuration tabs for an email account. The 'Incoming' tab is active, and the settings are as follows:

	INCOMING	OUTGOING
Protocol:	IMAP	SMTP
Server:	<input type="text"/>	<input type="text"/>
Port:	993	465
SSL:	SSL/TLS	SSL/TLS
Authentication:	Normal password	Normal password
Username:	<input type="text"/>	<input type="text"/>

At the bottom right of the dialog, there is a link for [Advanced config](#). At the bottom of the dialog, there are three buttons: 'Cancel', 'Re-test', and 'Done'. The 'Done' button is highlighted with a red border.

## (B) Update settings as below for POP3 and click <Done>

### <Incoming>

- Protocol : POP3
- Server : You can find it in Support Letter > Hosting Email > POP3 Server Host
- Port : 995
- SSL : SSL/TLS
- Authentication : Normal Password
- Username : Enter Email address

### <Outgoing>

- Server : You can find it in Support Letter > Hosting Email > SMTP Server Host
- Port : 465
- SSL : SSL/TLS
- Authentication : Normal Password
- Username : Enter Email address

	INCOMING	OUTGOING
Protocol:	POP3	SMTP
Server:	<input type="text"/>	<input type="text"/>
Port:	995	465
SSL:	SSL/TLS	SSL/TLS
Authentication:	Normal password	Normal password
Username:	<input type="text"/>	<input type="text"/>

[Advanced config](#)