



How to setup Email account in Windows Live Mail


1. Launch Windows Live Mail
2. Open menu




3. Go to Options > Email accounts



4. Click <Add>




5. Choose <Email Account> and click <Next>



6. Update settings as below and click <Next>

- Email address : Enter Email address
- Password : Enter Email account password
- Remember this password : Enable
- Display name for your sent messages : Enter sender name
- Manually configure server settings : Enable



The screenshot shows the 'Add your email accounts' window in Windows Live Mail. The window title is 'Windows Live Mail'. The main heading is 'Add your email accounts' in green. Below it, there is a sub-heading 'If you have a Windows Live ID, sign in now. If not, you can create one later.' and a link 'Sign in to Windows Live'. The form contains the following fields and options:

- Email address:** A text box containing 'someone@example.com'. Below it is a link 'Get a Windows Live email address'.
- Password:** An empty text box.
- Remember this password
- Display name for your sent messages:** A text box containing 'Example: John Doe'.
- Manually configure server settings

At the bottom right, there are two buttons: 'Cancel' and 'Next'. The 'Next' button is highlighted with a red border.


7. (A) Update settings as below for IMAP and click <Next>

<Incoming server information>

- Server type : IMAP
- Server address : You can find it in Support Letter > Hosting Email > IMAP Server Host
- Port : 993
- Requires a secure connection (SSL) : Enable
- Authenticate using : Clear text
- Login user name : Enter Email address

<Outgoing server information>

- Server address : You can find it in Support Letter > Hosting Email > SMTP Server Host
- Port : 465
- Requires a secure connection (SSL) : Enable
- Requires authentication : Enable



Windows Live Mail

Configure server settings

If you don't know your email server settings, contact your ISP or network administrator.

Incoming server information

Server type: IMAP

Server address: [] Port: 993

Requires a secure connection (SSL)

Authenticate using: Clear text

Logon user name: []

Outgoing server information

Server address: [] Port: 465

Requires a secure connection (SSL)

Requires authentication

Cancel Back Next


(B) Update settings as below for POP3 and click <Next>

<Incoming server information>

- Server type : POP
- Server address : You can find it in Support Letter > Hosting Email > POP3 Server Host
- Port : 995
- Requires a secure connection (SSL) : Enable
- Authenticate using : Clear text
- Login user name : Enter Email address

<Outgoing server information>

- Server address : You can find it in Support Letter > Hosting Email > SMTP Server Host
- Port : 465
- Requires a secure connection (SSL) : Enable
- Requires authentication : Enable



Windows Live Mail

Configure server settings

If you don't know your email server settings, contact your ISP or network administrator.

Incoming server information	Outgoing server information
Server type: <input type="text" value="POP"/>	Server address: <input type="text"/>
Server address: <input type="text"/>	Port: <input type="text" value="465"/>
<input checked="" type="checkbox"/> Requires a secure connection (SSL)	<input checked="" type="checkbox"/> Requires a secure connection (SSL)
Authenticate using: <input type="text" value="Clear text"/>	<input checked="" type="checkbox"/> Requires authentication
Logon user name: <input type="text"/>	

Cancel Back **Next**

8. Click <Finish>

